

# Console Messages ESY0070I - ESY0079W

Message	Explanation	Action
<b>ESY0070I</b> - CA SYSTEM ADAPTER DETECTED	During initialisation, the Computer Associates System Adapter was found to be active.	None. However, check to see that the CA-DYNAM/D API DYNACC. PHASE is accessible in the libraries specified in the LIBDEF PHASE SEARCH JCS statement.
<b>ESY0071W</b> - MESSAGE QUEUE LENGTH EXCEEDED - MESSAGES LOST	The VTAM incore message buffer has been filled. The startup parameter 'VTAMQLEN=' determines its length. The default is 100 (k).	Change value of VTAMQLEN and restart Entire System Server.
<b>ESY0072W</b> - OPEN FOR VTAM PRINTER ACB FAILED (ERROR=:1:)	An attempt to open the VTAM ACB whose name was specified in the startup parameter 'SPOOLACB=' has failed. Common errors are: 088 - Application name is already active. 090 - The application was not defined or is not active. Every minute, another attempt will be made. If the open is successful, the message <b>ESY0012I</b> will appear.	Contact your VTAM systems programmer.
<b>ESY0073W</b> Invalid command.	An invalid operator command was entered.	Correct it.
<b>ESY0074W</b> - NATURAL-SUB-TASK - SYSOUT ALLOCATION FAILED	An attempt to allocate a sysout dataset to contain output from Natural programs failed.	Please check job control of Entire System Server.
<b>ESY0076W</b> - NATURAL SUBTASK PARAMETER ERROR	A parameter passed to the NATURAL-SUB-TASK was in error.	Correct parameter error and retry.
<b>ESY0077W</b> - CANNOT LOAD NATURAL MODULE	The specified NATURAL-SUB-TASK module could not be loaded.	Check startup parameter NATMOD and the load libraries.
<b>ESY0078W</b> - GETMAIN ERROR	Storage requested via GETMAIN/GETVIS failed.	Run Entire System Server in a task with more memory.
<b>ESY0079W</b> - SECURITY CLASS OPERCMDS NOT DEFINED	The security class OPERCMDS is not defined to your external security system (RACF/ACF2/TSS etc).	Contact your systems programmer.